



***Monitoring the Leostream
Connecton Broker***

Restricted Rights Legend

The information contained in this document is confidential and subject to change without notice. No part of this document may be reproduced or disclosed to others without the prior permission of eG Innovations, Inc. eG Innovations, Inc. makes no warranty of any kind with regard to the software and documentation, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose.

Trademarks

Microsoft Windows, Windows NT, Windows 2003, and Windows 2000 are either registered trademarks or trademarks of Microsoft Corporation in United States and/or other countries.

The names of actual companies and products mentioned herein may be the trademarks of their respective owners.

Copyright

© 2008 eG Innovations, Inc. All rights reserved.

The copyright in this document belongs to eG Innovations, Inc. Complying with all applicable copyright laws is the responsibility of the user.

Table of Contents

MONITORING THE LEOSTREAM CONNECTION BROKER	1
1.1 THE CONNECTION BROKER SERVICE LAYER	3
1.1.1 <i>ConnectionBrokerStatus Test</i>	4
1.1.2 <i>ConnectionBrokerDatabase Test</i>	5
1.1.3 <i>ConnectionBrokerLogs Test</i>	7
1.1.4 <i>ConnectionBrokerCenters Test</i>	9
1.1.5 <i>WorkQueueStatus Test</i>	11
1.1.6 <i>SunRayConnections Test</i>	16
1.1.7 <i>VirtualDesktops Test</i>	19
1.2 CREATING A NEW ‘ADMINISTRATOR’ USER ON THE LEOSTREAM CONNECTION BROKER	22
CONCLUSION.....	25

Monitoring the Leostream Connection Broker

The Leostream Connection Broker is a robust and flexible session management tool that performs policy-based assignment of users to computing resources. Using this Connection Broker, you can provide end users with access to data and desktops from a wide range of clients.

In the Connection Broker, you first define:

- **Desktops:** Virtual machines, physical machines, and Microsoft® Terminal Services that you want to make available for assignment to end users.
- **Applications:** Applications hosted in a Citrix XenApp farm, that you want to assign to end users.
- **Centers:** A group of desktops or applications registered with the Connection Broker from external systems.
- **Pools:** Collections of desktops or applications, gathered from a single or multiple centers.
- **Policies:** Rules that assign desktops and applications to users and define what happens when the assignment is done.
- **Roles:** Permissions that control the level of access an end users has to different features in the Connection Broker interface.

Then, you create rules that map end users to roles and policies, which in turn determine which Desktops the user is assigned and what level of access the user has to the Connection Broker interface. The Connection Broker maps users to rules via their authentication server attributes, allowing you to authenticate users against existing Active Directory, Novell® eDirectory™, or OpenLDAP™ directory services.

Monitoring Leostream Connection Brokers




Figure 1: Assignment of desktops and applications from a pool to a user via assignment rules

The users of today are intolerant towards access delays, regardless of how rarely it occurs, or where they are accessing the data/desktops from - whether from a thin client, fat client, Web browser, or from within or outside a firewall. The result? Even the slightest of deviations in the performance of the Leostream Connection Broker would result in considerable loss of reputation and revenue. For instance, say, the Connection Broker is used in a virtualized environment to provide users with access to virtual machines. In such an environment, if the Connection Broker is unavailable, or is available, but processes jobs very slowly, the user experience with the virtualized infrastructure as a whole will suffer. To avoid such adversities, continuous monitoring of the Leostream Connection Broker is imperative.

eG Enterprise prescribes a specialized *Leostream CB* monitoring model that provides 24 x 7 monitoring of the Connection Broker.




Figure 2: Layer model of the Virtual Desktop Manager

Each layer of Figure 2 is mapped to a series of tests that report a wide variety of performance metrics. The **Operating System** layer monitors the CPU, memory, and disk resources used on the operating system that the Connection Broker is running on. The **Network** layer monitors connectivity and traffic to and from the Connection Broker system. **TCP** traffic activity is tracked by the TCP layer, and the status of the key Connection Broker processes (e.g., the web server, the application server, etc.) is tracked by the **Application Processes** layer. The metrics associated with each of these layers are dealt with extensively in the *Monitoring Generic Servers* document.

The **Connection Broker Service** layer collects metrics specific to the Leostream Connection Broker. Using these metrics, administrators can find quick and easy answers to the following performance queries:

- Is the Connection Broker available? How quickly is it responding to requests?
- Is the web server component of the Connection Broker available?
- Are the internal and external databases of the Connection Broker available?
- Are the databases responding quickly to queries?
- Were any errors reported in the Connection Broker logs?
- What is the current status of each center from which the Connection Broker gathers desktops, physical machines, etc.?
- How many jobs are in the work queue? Are there too many pending jobs?
- Did any job abort suddenly?
- Are the Sun Ray servers connected to the Connection Broker active?
- How many VMs are registered with the Connection Broker? How many of these VMs are simultaneously active and how many VMs are available to handle new requests from users?

The metrics associated with the Connection Broker Service layer are discussed in detail below.

1.1 The Connection Broker Service Layer

The tests mapped to this layer monitor the overall health of the key components of the Connection Broker such as the database, the centers, the work queues, the log files, etc., and also report whether the Connection Broker is available or not.

eG Enterprise monitors Leostream in 2 ways - by deploying the eG agent on the connection broker itself, or by deploying the eG agent on any remote Windows host in the environment and configuring it to remotely monitor Leostream. While the former is termed "agent-based" monitoring, the latter is called "agentless" monitoring as it does not require an eG agent to be present on the target connection broker

In either case, the eG agent uses the Connection Broker's web query interface to connect to it and collect metrics. HTTP or HTTPS can be used for communication between the eG agent and the Connection Broker, and the administrator's credentials (i.e., user name and password) must be specified when configuring the Connection Broker for monitoring, so that the eG agent can connect to the Connection Broker and obtain metrics.




Figure 3: The tests mapped to the Connection Broker Service layer

1.1.1 ConnectionBrokerStatus Test

The 24x7 availability of the Connection Broker is imperative to ensure that end-users have uninterrupted access to desktops/data and critical computing resources. A Connection Broker might be rendered unavailable owing to many reasons – eg., an internal configuration error, a database error, the non-availability of the Connection Broker’s web interface, etc. While the knowledge of the failure of a Connection Broker is valuable to an administrator, knowing what caused the failure can alone help the administrator quickly resolve the issue and restore the Connection Broker to normalcy.

The ConnectionBrokerStatus test instantly informs administrators of the non-availability (if any) of the Connection Broker, reports whether it is owing to the web service being down, and also intimates them of any probable slowdown in the responsiveness of the server.

Purpose	Instantly informs administrators of the non-availability (if any) of the Connection Broker, reports whether it is owing to the web service being down, and also intimates them of any probable slowdown in the responsiveness of the server;
Target of the test	A Leostream Connection Broker
Agent deploying the test	An external agent

Configurable parameters for the test	<ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured 3. PORT – Refers to the port used by the Connection Broker is listening. 4. SSL – By default, this flag is set to No, indicating that by default, the test connects to the Connection Broker via HTTP. If the Connection Broker is SSL-enabled, then set this flag to Yes. 5. TIMEOUT – Specify the duration (in seconds) within which the test should timeout. The default duration is 30 seconds. 														
Outputs of the test	One set of results for the Connection Broker being monitored														
Measurements made by the test	<table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="width: 50%; text-align: center;">Measurement</th> <th style="width: 20%; text-align: center;">Measurement Unit</th> <th style="width: 30%; text-align: center;">Interpretation</th> </tr> </thead> <tbody> <tr> <td data-bbox="428 688 751 932"> Connection broker service availability: Indicates whether/not the Connection Broker service is available. </td> <td data-bbox="751 688 966 932" style="text-align: center;">Percent</td> <td data-bbox="966 688 1482 932"> The value 100 indicates that the Connection Broker is available. If the value is 0, it indicates that the connection broker is not available. This could be owing to an internal error, or if the database is inaccessible, or a poor network connection. </td> </tr> <tr> <td data-bbox="428 932 751 1297"> Web service availability: Indicates whether the web server part of the Connection Broker is available or not. </td> <td data-bbox="751 932 966 1297" style="text-align: center;">Percent</td> <td data-bbox="966 932 1482 1297"> The value 100 indicates that the web server is available. If the value is 0, it indicates that the web server is not available. In the event of the non-availability of the Connection Broker, you can use the value of this measure to determine whether the Connection Broker failure occurred because the web server was deliberately/inadvertently stopped or had failed due to some errors. </td> </tr> <tr> <td data-bbox="428 1297 751 1566"> Response time: Indicates the time taken by the Connection Broker to respond to requests. </td> <td data-bbox="751 1297 966 1566" style="text-align: center;">Secs</td> <td data-bbox="966 1297 1482 1566"> Ideally, this value should be low. Sporadic spikes or a steady increase in this value is a cause for concern as it indicates deterioration in the performance of the Connection Broker. This could be owing to improper configuration of the broker or when the broker experiences an overload. </td> </tr> </tbody> </table>	Measurement	Measurement Unit	Interpretation	Connection broker service availability: Indicates whether/not the Connection Broker service is available.	Percent	The value 100 indicates that the Connection Broker is available. If the value is 0, it indicates that the connection broker is not available. This could be owing to an internal error, or if the database is inaccessible, or a poor network connection.	Web service availability: Indicates whether the web server part of the Connection Broker is available or not.	Percent	The value 100 indicates that the web server is available. If the value is 0, it indicates that the web server is not available. In the event of the non-availability of the Connection Broker, you can use the value of this measure to determine whether the Connection Broker failure occurred because the web server was deliberately/inadvertently stopped or had failed due to some errors.	Response time: Indicates the time taken by the Connection Broker to respond to requests.	Secs	Ideally, this value should be low. Sporadic spikes or a steady increase in this value is a cause for concern as it indicates deterioration in the performance of the Connection Broker. This could be owing to improper configuration of the broker or when the broker experiences an overload.		
	Measurement	Measurement Unit	Interpretation												
	Connection broker service availability: Indicates whether/not the Connection Broker service is available.	Percent	The value 100 indicates that the Connection Broker is available. If the value is 0, it indicates that the connection broker is not available. This could be owing to an internal error, or if the database is inaccessible, or a poor network connection.												
Web service availability: Indicates whether the web server part of the Connection Broker is available or not.	Percent	The value 100 indicates that the web server is available. If the value is 0, it indicates that the web server is not available. In the event of the non-availability of the Connection Broker, you can use the value of this measure to determine whether the Connection Broker failure occurred because the web server was deliberately/inadvertently stopped or had failed due to some errors.													
Response time: Indicates the time taken by the Connection Broker to respond to requests.	Secs	Ideally, this value should be low. Sporadic spikes or a steady increase in this value is a cause for concern as it indicates deterioration in the performance of the Connection Broker. This could be owing to improper configuration of the broker or when the broker experiences an overload.													

1.1.2 ConnectionBrokerDatabase Test

The Connection Broker is completely self-contained and is bundled with an internal database. This database stores and maintains the following:

- Passwords only for users that are created locally
- Clients

Monitoring Leostream Connection Brokers

- Desktops and their environments
- Microsoft Active Directory® user credentials: Encrypted.
- Machine centers: Access credentials are encrypted.
- Locations, roles, and all other operational parameters

An external database, on the other hand, is required when Connection Brokers are clustered. To handle high peak loads (such as, simultaneous logons) and failure of a Connection Broker (or its host) it is necessary to cluster Connection Brokers and run each Connection Broker on a different virtualization host. As soon as you cluster Connection Brokers virtual machines, they need an external database in order to share information. Microsoft SQL Server® can be used as an external database server for the Connection Broker.

A key component of the Connection Broker is its internal and external database servers. If the internal/external database is rendered unavailable or is experiencing a significant slowdown, it can cause prolonged Connection Broker outages, deny/delay users access to critical desktops/data, and thus mar the user experience. Using the CBDatabase test, administrators can periodically monitor the availability and responsiveness of the local and remote databases, be proactively alerted to anomalies, and avert adversities in time.

Purpose	Periodically monitors the availability and responsiveness of the local and remote databases, be proactively alerted to anomalies, and avert adversities in time;		
Target of the test	A Leostream Connection Broker		
Agent deploying the test	An internal agent		
Configurable parameters for the test	<ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured 3. PORT - Refers to the port used by the Connection Broker is listening. 4. SSL - By default, this flag is set to No, indicating that by default, the test connects to the Connection Broker via HTTP. If the Connection Broker is SSL-enabled, then set this flag to Yes. 5. TIMEOUT - Specify the duration (in seconds) within which the test should timeout. The default duration is 30 seconds. 		
Outputs of the test	One set of results each for the local and remote database used by the Connection Broker		
Measurements made by the test	Measurement	Measurement Unit	Interpretation

test	Availability: Indicates whether the database is available or not.	Percent	While the value 100 indicates that the database is available, the value 0 indicates that it is not. The internal database will be available as long as the Connection Broker is. If the external database is unavailable, it could be owing to an improper configuration of the database or a poor network connection (in case of an external database).
	Response time: Indicates the time taken by the connection broker to respond to requests.	Secs	Ideally, the value of this measure should be low. A very high value indicates a marked deterioration in the performance of the database, which can be attributed to insufficient space, improper configuration, or a network congestion (in case of an external database).

1.1.3 ConnectionBrokerLogs Test

The Connection Broker maintains a record of all activities it performs in log files. The logs show the different stages of user connection - e.g., when a user signs in, is offered and assigned a Desktop, logs out, etc. Using the logs, administrators can:

- Diagnose problems with your policy logic related to power and assignment controls, by looking at logs related to powering up and down Desktops, and releasing desktops back to the pool.
- Monitor the system load, such as the number of logins over a period of time.
- Monitor user access

The ConnectionBrokerLogs test monitors the logs and alerts administrators to error/warning events that are captured by the logs.

Purpose	Monitors the logs and alerts administrators to error/warning events that are captured by the logs
Target of the test	A Leostream Connection Broker
Agent deploying the test	An internal agent

<p>Configurable parameters for the test</p>	<ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured 3. PORT – Refers to the port used by the Connection Broker is listening. 4. SSL – By default, this flag is set to No, indicating that by default, the test connects to the Connection Broker via HTTP. If the Connection Broker is SSL-enabled, then set this flag to Yes. 5. USER – To enable the test to log into the Connection Broker and extract statistics of interest from it, specify the login name of a user on the Connection Broker who is assigned the Administrator role. If need be, you can even create a special Administrator user on the Connection Broker for this purpose, and pass the credentials of that user to the test. Refer to Section 1.2 to know how to create such a user. 6. PASSWORD – Specify the password of the USER here. 7. CONFIRM PASSWORD – Confirm the PASSWORD by retyping it here. 8. DD FREQUENCY - Refers to the frequency with which detailed diagnosis measures are to be generated for this test. The default is <i>1:1</i>. This indicates that, by default, detailed measures will be generated every time this test runs, and also every time the test detects a problem. You can modify this frequency, if you so desire. Also, if you intend to disable the detailed diagnosis capability for this test, you can do so by specifying <i>none</i> against DD FREQUENCY. 9. TIMEOUT - Specify the duration (in seconds) within which the test should timeout. The default duration is 30 seconds. 10. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled: <ul style="list-style-type: none"> ➤ The eG manager license should allow the detailed diagnosis capability ➤ Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. 		
<p>Outputs of the test</p>	<p>One set of results for each of the Connection Broker logs being monitored</p>		
<p>Measurements made by the test</p>	<p style="text-align: center;">Measurement</p>	<p style="text-align: center;">Measurement Unit</p>	<p style="text-align: center;">Interpretation</p>
	<p>Information events: Indicates the number of information events that were logged in the log currently.</p>	<p>Number</p>	<p>The detailed diagnosis of this measure reveals the details of the information events.</p>

	<p>Warnings:</p> <p>Indicates the number of warning events recorded in the log, currently.</p>	Number	Ideally, this value should be 0. If a non-zero value is reported, use the detailed diagnosis capability of this measure to know more about the warning event.
	<p>Errors:</p> <p>Indicates the number of error events that were currently recorded in the log.</p>	Number	Ideally, this value should be 0. A non-zero value warrants further investigation. You can then use the detailed diagnosis capability of this measure to know more about the error event.

1.1.4 ConnectionBrokerCenters Test

The Connection Broker adds Desktops through a process called *discovery*, i.e., gathering available resources from external systems. The Connection Broker can discover:

- Microsoft® Windows® Terminal Services Servers and Desktops using the Leostream Agent
- Virtual Desktops from the virtualization host or virtualization management system
- Physical machines registered in a Microsoft Active Directory® server
- Applications hosted by a Citrix XenApp server

The external systems from which Desktop are discovered are called *centers*.

This test auto-discovers all the centers on a Connection Broker, and reports the current status of each. Besides user-configured centers, the test also reports the status of an **Uncategorized center**; this center contains Desktops running the Leostream Agents, which are not cataloged by another center. The **Uncategorized** center allows you to:

- Add physical machines without creating an Active Directory center
- Add a virtual machine that is part of a non-natively supported hypervisor, such as Microsoft Hyper-Vi

Purpose	Auto-discovers all the centers on a Connection Broker, and reports the current status of each
Target of the test	A Leostream Connection Broker
Agent deploying the test	An internal agent

<p>Configurable parameters for the test</p>	<ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured 3. PORT – Refers to the port used by the Connection Broker is listening. 4. SSL – By default, this flag is set to No, indicating that by default, the test connects to the Connection Broker via HTTP. If the Connection Broker is SSL-enabled, then set this flag to Yes. 5. USER – To enable the test to log into the Connection Broker and extract statistics of interest from it, specify the login name of a user on the Connection Broker who is assigned the Administrator role. If need be, you can even create a special Administrator user on the Connection Broker for this purpose, and pass the credentials of that user to the test. Refer to Section 1.2 to know how to create such a user. 6. PASSWORD – Specify the password of the USER here. 7. CONFIRM PASSWORD – Confirm the PASSWORD by retyping it here. 8. TIMEOUT – Specify the duration (in seconds) within which the test should timeout. The default duration is 30 seconds. 9. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. <p>The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled:</p> <ul style="list-style-type: none"> ➤ The eG manager license should allow the detailed diagnosis capability ➤ Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. 																			
<p>Outputs of the test</p>	<p>One set of results for each of the Connection Broker centers being monitored</p>																			
<p>Measurements made by the test</p>	<table border="1"> <thead> <tr> <th data-bbox="428 1329 751 1413">Measurement</th> <th data-bbox="751 1329 964 1413">Measurement Unit</th> <th colspan="2" data-bbox="964 1329 1482 1413">Interpretation</th> </tr> </thead> <tbody> <tr> <td data-bbox="428 1413 751 1856" rowspan="3"> <p>Status of the CB Center:</p> <p>Indicates the current status of the center.</p> </td> <td data-bbox="751 1413 964 1856" rowspan="3"> <p>Boolean</p> </td> <td colspan="2" data-bbox="964 1413 1482 1486"> <p>The status indicators and what they represent are discussed below:</p> </td> </tr> <tr> <td data-bbox="964 1486 1073 1539"> <p>Status</p> </td> <td data-bbox="1073 1486 1240 1539"> <p>Definition</p> </td> <td data-bbox="1240 1486 1482 1539"> <p>Description</p> </td> </tr> <tr> <td data-bbox="964 1539 1073 1686"> <p>1</p> </td> <td data-bbox="1073 1539 1240 1686"> <p>Online</p> </td> <td data-bbox="1240 1539 1482 1686"> <p>Indicates the center is operating normally</p> </td> </tr> <tr> <td data-bbox="964 1686 1073 1856"> <p>2</p> </td> <td data-bbox="1073 1686 1240 1856"> <p>Offline</p> </td> <td data-bbox="1240 1686 1482 1856"> <p>Indicates that the Connection Broker is unable to contact the center</p> </td> </tr> </tbody> </table>	Measurement	Measurement Unit	Interpretation		<p>Status of the CB Center:</p> <p>Indicates the current status of the center.</p>	<p>Boolean</p>	<p>The status indicators and what they represent are discussed below:</p>		<p>Status</p>	<p>Definition</p>	<p>Description</p>	<p>1</p>	<p>Online</p>	<p>Indicates the center is operating normally</p>	<p>2</p>	<p>Offline</p>	<p>Indicates that the Connection Broker is unable to contact the center</p>		
Measurement	Measurement Unit	Interpretation																		
<p>Status of the CB Center:</p> <p>Indicates the current status of the center.</p>	<p>Boolean</p>	<p>The status indicators and what they represent are discussed below:</p>																		
		<p>Status</p>	<p>Definition</p>	<p>Description</p>																
		<p>1</p>	<p>Online</p>	<p>Indicates the center is operating normally</p>																
<p>2</p>	<p>Offline</p>	<p>Indicates that the Connection Broker is unable to contact the center</p>																		

Monitoring Leostream Connection Brokers

			3	Needs Upgrade	Indicates that the Leostream Agent in this center needs to be upgraded. This setting applies only for centers that use the Leostream Agent.
			4	Disk Full	Indicates that the center's disk is full
			5	Refreshing	Indicates that the Connection Broker is refreshing the contents of this center
	Is CB center active? Indicates whether the center is active or inactive currently.	Number	If this measure reports the value 1, it indicates that the center is active. The value 0 indicates that the center is inactive.		

1.1.5 WorkQueueStatus Test

The job queue contains Connection Broker processes that are independent of the Web interface. When the Connection Broker is not functioning correctly, you can use the job queue as a diagnostics tool. For instance, if you requested an action and it has not taken place, check if the action is pending in the job queue.

The WorkQueueStatus test monitors the job queues and reports the status of jobs queued on the Connection Broker.

Purpose	Monitors the job queues and reports the status of jobs queued on the Connection Broker;
Target of the test	A Leostream Connection Broker
Agent deploying the test	An internal agent

<p>Configurable parameters for the test</p>	<ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured 3. PORT – Refers to the port used by the Connection Broker is listening. 4. SSL – By default, this flag is set to No, indicating that by default, the test connects to the Connection Broker via HTTP. If the Connection Broker is SSL-enabled, then set this flag to Yes. 5. USER – To enable the test to log into the Connection Broker and extract statistics of interest from it, specify the login name of a user on the Connection Broker who is assigned the Administrator role. If need be, you can even create a special Administrator user on the Connection Broker for this purpose, and pass the credentials of that user to the test. Refer to Section 1.2 to know how to create such a user. 6. PASSWORD – Specify the password of the USER here. 7. CONFIRM PASSWORD – Confirm the PASSWORD by retyping it here. 8. SHOWFINISHEDD – This test also reports the number of jobs in the queue that were recently completed. The detailed diagnosis of this measure, if enabled, will provide the details of all the newly finished jobs. In some environments, the count of the newly finished jobs could run to a thousand. In such environments naturally, the detailed diagnosis data for this measure, if available, will consume a considerable amount of database space, and can sometimes even choke the database. To reduce the strain on the database, the eG agent, by default, does not collect detailed diagnosis information for the <i>New finished jobs</i> measure. Accordingly, the SHOWFINISHEDDD flag is set to No, by default. If you want to view the detailed diagnosis for this measure, then set this flag to Yes. 9. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled: <ul style="list-style-type: none"> ➤ The eG manager license should allow the detailed diagnosis capability ➤ Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. 10. TIMEOUT - Specify the duration (in seconds) within which the test should timeout. The default duration is 30 seconds. 		
<p>Outputs of the test</p>	<p>One set of results for the Connection Broker being monitored</p>		
<p>Measurements made by the test</p>	<p style="text-align: center;">Measurement</p>	<p style="text-align: center;">Measurement Unit</p>	<p style="text-align: center;">Interpretation</p>

Monitoring Leostream Connection Brokers

	<p>Total jobs: Indicates the total number of jobs that are currently in queue.</p>	Number	This measure is a good indicator of the workload on the Connection Broker.
	<p>Waiting jobs: Indicates the number of jobs that are currently waiting.</p>	Number	Waiting jobs are those jobs that are pending execution. If the number of pending jobs is very high, it could indicate a processing bottleneck on the Connection Broker. Use the detailed diagnosis of this measure to know which jobs are pending, and their related details.
	<p>Inprogress jobs: Indicates the number of jobs that are currently executing.</p>	Number	The detailed diagnosis of this measure reveals the details of jobs that are currently in progress.
	<p>Finished jobs: Indicates the number of jobs that have completed execution currently.</p>	Number	
	<p>Aborted jobs: Indicates the number of jobs that aborted currently.</p>	Number	<p>This measure refers to those jobs that stopped executing on their own.</p> <p>Ideally, the value of this measure should be low. A high value could indicate a problem condition. You can use the detailed diagnosis of this measure to view the list of aborted jobs and investigate the reasons behind the abnormal termination of the jobs.</p>
	<p>Cancelled jobs: Indicates the number of jobs that were currently cancelled.</p>	Number	An upcoming job that is terminated by the user is considered a cancelled job. To view the list of the jobs that were cancelled, use the detailed diagnosis of this measure.
	<p>Increase in qlength: Indicates the number of jobs that were newly added to the queue in this measurement period.</p>	Number	While the total number of jobs in the work queue is useful, of more importance is whether the number of jobs in the work queue is increasing or decreasing. A consistent increase in length of the work queue may indicate that the Connection Broker is starting to bottleneck. Check the increase in pending and finished jobs. If the pending jobs in the work queue are increasing, this is a clear sign of a bottleneck on the Connection Broker.

Monitoring Leostream Connection Brokers

	<p>New wait jobs:</p> <p>Indicates the number of new pending jobs in the queue in this measurement period.</p>	Number	If there is a sudden/gradual increase in the value of this measure, it could indicate a processing bottleneck on the Connection Broker. Use the detailed diagnosis of this measure to know the new pending jobs and their related details.
	<p>New inprogress jobs:</p> <p>Indicates the number of new jobs in execution in this measurement period.</p>	Number	The detailed diagnosis of this measure provides the details of the jobs that are in progress in this measurement period.
	<p>New finish jobs:</p> <p>Indicates the number of jobs that finished execution in this measurement period.</p>	Number	The detailed diagnosis of this measure provides the details of the newly finished jobs. Note that the detailed diagnosis for this measure will be available only if the SHOWFINISHEDDD flag is set to Yes.
	<p>New abort jobs:</p> <p>Indicates the number of the jobs that were newly aborted in this measurement period.</p>	Number	Ideally, the value of this measure should be low. A high value could indicate a problem condition. You can use the detailed diagnosis of this measure to view the list of newly aborted jobs and investigate the reasons behind the abnormal termination of the jobs.
	<p>New cancel jobs:</p> <p>Indicates the number of jobs that were newly cancelled.</p>	Number	The detailed diagnosis of this measure provides the details of the newly cancelled jobs.

The detailed diagnosis of the *Waiting jobs* measure reveals the details of all jobs that are currently pending in the worker queue of the Connection Broker. The details displayed include:

- The name of the user who requested the job
- The ID of the job following which this job should run
- The ID and name of the object on which the job should be performed
- The name of the job/action
- The parameters to be passed to the action
- The time at which the job is to be executed
- The result of the job; whether successful or not
- Data and time at which the processing of the job was begun by the queue
- Data and time at which the processing of the job was completed by the queue
- The PID of the work queue that controls the job
- The site ID, if the test connects to a remote database
- The number of times the job has run

Monitoring Leostream Connection Brokers

Using this information, administrators can accurately identify the pending jobs, and also determine the users who have initiated the jobs. This information helps administrators in investigating the reasons for the delay in job processing.

Time	UserId	RunAfter	ObjectType	ObjectName	Action	Param	RunAt	Result	Start	Finish	WorkQueueId	SiteId	RunCou
Sep 17, 2008 12:37:34	-	0	VC2	egCenter1	poll	-	2008-09-17 12:34:45	0	2008-09-17 12:33:42	2008-09-17 12:33:45	31169	0	3301
	-	0	Ntp_server	NTP Time server	sync	-	2008-09-17 13:12:09	0	2008-09-17 12:12:09	2008-09-17 12:12:09	27506	0	26

Figure 4: The detailed diagnosis of the Waiting jobs measure

The detailed diagnosis of the *Inprogress jobs* measure reveals the details of all jobs that are currently executing on the Connection Broker.

Time	UserId	RunAfter	ObjectType	ObjectName	Action	Param	RunAt	Result	Start	Finish	WorkQueueId	SiteId	RunCou
Sep 17, 2008 11:34:14	-	0	VC2	egCenter1	poll	-	2008-09-17 11:30:41	0	2008-09-17 11:30:42	2008-09-17 11:29:41	20632	0	3241

Figure 5: The detailed diagnosis of the Inprogress jobs measure

The detailed diagnosis of the *Aborted jobs* measure reveals the details of all jobs that have stopped executing currently, without being manually terminated by the user. By analyzing this information, administrators can zero-in on the reasons for the abnormal termination of a job, and ensure such process abortions do not recur.

Time	UserId	RunAfter	ObjectType	ObjectName	Action	Param	RunAt	Result	Start	Finish	WorkQueueId	SiteId	RunCou
Sep 17, 2008 12:37:34	-	0	VC2	egCenter1	poll	-	2008-09-14 12:20:19	0	2008-09-14 12:18:34	2008-09-14 12:19:19	13851	0	395
	-	0	Maintenance	-	system_check	-	2008-09-16 11:12:07	-	2008-09-16 11:12:08	-	1727	0	1
	-	0	VC2	egCenter1	poll	-	2008-09-13 13:43:47	0	2008-09-13 13:42:02	2008-09-13 13:42:47	17387	0	167
	-	0	VC2	egCenter1	poll	-	2008-09-14 00:37:44	0	2008-09-14 00:36:20	2008-09-14 00:36:44	15924	0	470

Figure 6: The detailed diagnosis of the Aborted jobs measure

Monitoring Leostream Connection Brokers

The detailed diagnosis of the *New inprogress jobs* measure reveals the details of the recent additions to the list of jobs that are in progress.




Figure 7: The detailed diagnosis of the New Inprogress jobs measure

1.1.6 SunRayConnections Test

Sun Ray is a stateless thin-client solution from Sun Microsystems, Inc., that is aimed at corporate environments.

The Sun Ray architecture consists of two components: the Sun Ray thin client DTU (desktop unit) and the Sun Ray Server Software. The Sun Ray DTU is typically a display device that requires no desktop administration yet provides the experience users expect from a high-end workstation. With the Sun Ray smart card interface, a user simply inserts a smart card into any available Sun Ray thin client and instantaneously accesses an existing session.

The Sun Ray Server Software provides user authentication and encryption between server and client as well as user session management. It not only enhances security, but also helps reduce the complexity and administration of the IT environment.

The Leostream Connection Broker can be configured to interact with the Sun Ray server software, so that users connecting via the Sun Ray thin client DTU are provided with easy and instant access to remote VMs. Figure 12 depicts how the Leostream Connection Broker works with the Sun Ray server.

Monitoring Leostream Connection Brokers




Figure 8: The Leostream Connection Broker

Once a user inserts his smart card into the Sun Ray DTU, the DTU reads the card and sends the unique card token to the Sun Ray Server Software (SRSS) component on the Sun Ray server via the highly efficient Sun Appliance Link Protocol (ALP). Upon receipt of the token, the Sun Ray server automatically launches Leostream Connect for Linux, where the users enter their authentication credentials. Leostream Connect then passes the user credentials to the Leostream Connection Broker which looks up the user in the authentication server, determines which policies to apply, and offers Desktops. Using Leostream Connect, the user selects which desktop to log in to. Leostream Connect passes this information to the Connection Broker.

The Connection Broker also sends Leostream Connect the list of Sun Ray servers associated with the VirtualCenter cluster on which the selected desktop sits. If a switch is needed, the Connection Broker picks a random Sun Ray server from the list and redirects the DTU to this host. The client launches one or more RDP sessions using the Sun Ray Connector for Windows. Using this setup, the high-latency link to the SRSS is traversed using ALP and the low latency link between the SRSS server and the Desktop is crossed using RDP, with the SRSS server acts as a proxy. In the end, each user has his/her own DTU connected to a Sun Ray server, and the Sun Ray Connector for Windows connects them to a Desktop using the RDP protocol.

This test monitors the SunRay servers that the Connection Broker has discovered from VC clusters, and reports the status of each server.

Purpose	Monitors the SunRay servers that the Connection Broker has discovered from VC clusters, and reports the status of each server
Target of the test	A Leostream Connection Broker
Agent deploying the test	An internal agent

<p>Configurable parameters for the test</p>	<ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured 3. PORT – Refers to the port used by the Connection Broker is listening. 4. SSL – By default, this flag is set to No, indicating that by default, the test connects to the Connection Broker via HTTP. If the Connection Broker is SSL-enabled, then set this flag to Yes. 5. USER – To enable the test to log into the Connection Broker and extract statistics of interest from it, specify the login name of a user on the Connection Broker who is assigned the Administrator role. If need be, you can even create a special Administrator user on the Connection Broker for this purpose, and pass the credentials of that user to the test. Refer to Section 1.2 to know how to create such a user. 6. PASSWORD – Specify the password of the USER here. 7. CONFIRM PASSWORD – Confirm the PASSWORD by retyping it here. 8. TIMEOUT – Specify the duration (in seconds) within which the test should timeout. The default duration is 30 seconds. 9. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. <p>The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled:</p> <ul style="list-style-type: none"> ➤ The eG manager license should allow the detailed diagnosis capability ➤ Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. 		
<p>Outputs of the test</p>	<p>One set of results for each Sun Ray client managed by the Connection Broker</p>		
<p>Measurements made by the test</p>	<p style="text-align: center;">Measurement</p>	<p style="text-align: center;">Measurement Unit</p>	<p style="text-align: center;">Interpretation</p>
	<p>Is the server alive? Indicates whether the SunRay server is currently available for use or not.</p>	<p>Boolean</p>	<p>If the Sun Ray host is free, then this measure will report the value 1. If the Sun Ray host is not available, then the measure will report the value 0.</p>
	<p>Is the Sun Ray host active? Indicates whether the Sun Ray client is currently active or not.</p>	<p>Boolean</p>	<p>If the Sun Ray host is being actively used, then this measure will report the value 1. If the Sun Ray host is available but not actively used, then the measure will report the value 0.</p>

1.1.7 VirtualDesktops Test

Typically, the Leostream Connection Broker provides users access to desktops based on access policies defined in the authentication server. Some users might possess exclusive access rights to specific desktops - in other words, some desktops could be 'hard-assigned' to certain users, such that every other user would be denied access to those desktops. As the number of desktops registered with the Connection Broker changes dynamically, at any given point in time, administrators might want to know the number of hard-assigned and policy-driven desktops that are been actively used by users, and the number that is free, so that they can plan desktop assignments accordingly and ensure that no user runs out of desktops. The VirtualDesktops test enables administrators to figure out the total number of hard-assigned and policy-driven desktops registered with the Connection Broker, and helps them assess their status and usage. The measures made by this test are as follows:

Purpose	Enables administrators to figure out the total number of hard-assigned and policy-driven desktops registered with the Connection Broker, and helps them assess their status and usage
Target of the test	A Leostream Connection Broker
Agent deploying the test	An internal agent

<p>Configurable parameters for the test</p>	<ol style="list-style-type: none"> 1. TEST PERIOD - How often should the test be executed 2. HOST - The host for which the test is to be configured 3. PORT – Refers to the port used by the Connection Broker is listening. 4. SSL – By default, this flag is set to No, indicating that by default, the test connects to the Connection Broker via HTTP. If the Connection Broker is SSL-enabled, then set this flag to Yes. 5. USER – To enable the test to log into the Connection Broker and extract statistics of interest from it, specify the login name of a user on the Connection Broker who is assigned the Administrator role. If need be, you can even create a special Administrator user on the Connection Broker for this purpose, and pass the credentials of that user to the test. Refer to Section 1.2 to know how to create such a user. 6. PASSWORD – Specify the password of the USER here. 7. CONFIRM PASSWORD – Confirm the PASSWORD by retying it here. 8. TIMEOUT – Specify the duration (in seconds) within which the test should timeout. The default duration is 30 seconds. 9. DD FREQUENCY - Refers to the frequency with which detailed diagnosis measures are to be generated for this test. The default is <i>1:1</i>. This indicates that, by default, detailed measures will be generated every time this test runs, and also every time the test detects a problem. You can modify this frequency, if you so desire. Also, if you intend to disable the detailed diagnosis capability for this test, you can do so by specifying <i>none</i> against DD FREQUENCY. 10. DETAILED DIAGNOSIS - To make diagnosis more efficient and accurate, the eG Enterprise suite embeds an optional detailed diagnostic capability. With this capability, the eG agents can be configured to run detailed, more elaborate tests as and when specific problems are detected. To enable the detailed diagnosis capability of this test for a particular server, choose the On option. To disable the capability, click on the Off option. The option to selectively enable/disable the detailed diagnosis capability will be available only if the following conditions are fulfilled: <ul style="list-style-type: none"> ➤ The eG manager license should allow the detailed diagnosis capability ➤ Both the normal and abnormal frequencies configured for the detailed diagnosis measures should not be 0. 		
<p>Outputs of the test</p>	<p>One set of results for <i>Policy_drive_VMs</i> and one for <i>User_assigned_VMs</i> being monitored</p>		
<p>Measurements made by the test</p>	<p style="text-align: center;">Measurement</p>	<p style="text-align: center;">Measurement Unit</p>	<p style="text-align: center;">Interpretation</p>
	<p>Total desktops: Indicates the total number of desktops registered with the Connection Broker.</p>	<p>Number</p>	

Monitoring Leostream Connection Brokers

	<p>Powered desktops: Indicates the number of desktops that are currently powered on.</p>	Number	
	<p>Available desktops: Indicates the number of desktops that are currently available for assignment to users.</p>	Number	<p>For instance, of a total of 10 desktops, if 6 are currently powered on and 1 is in maintenance, then it indicates that 5 (6-1) desktops are available for assignment to users.</p> <p>Use the detailed diagnosis of this measure to know which desktops are currently available.</p>
	<p>Desktops with users: Indicates the number of desktops that are currently assigned to users.</p>	Number	Use the detailed diagnosis of this measure to know which running desktops are in use.
	<p>Free desktops: Indicates the number of desktops to which no users are currently logged in.</p>	Number	
	<p>Percent desktops with users: Indicates the percentage of available desktops that are currently assigned to users.</p>	Percent	A very high value of this measure could indicate that subsequent users might not have desktops to access.
	<p>Unused desktops: Indicates the number of registered desktops that are not assigned to any user.</p>	Number	
	<p>Percent unused desktops: Indicates the percentage of desktops that are not assigned to users.</p>	Percent	

1.2 Creating a New ‘Administrator’ User on the Leostream Connection Broker

The eG agent logs into the Leostream Connection Broker to extract metrics of interest from it. To facilitate this login, most of the tests executed by the eG agent need to be configured with the credentials of a user to the Connection Broker who has **Administrator** privileges. You can either provide the login details of an existing **Administrator** or create a new user for this purpose. The steps below discuss how to create a new user on the Leostream Connection Broker, and assign **Administrator** privileges to that user.

1. Connect to the Connection Broker using the URL: **http://<ConnectionBrokerIP>/** or **https://<ConnectionBrokerIP>/**
2. When the login screen appears, login as an **Administrator**. The default administrator is *admin* with password *leo*.



Figure 9: The login page

3. When the Leostream admin console appears, click on the **Users** link at the top of the console to view the list of users registered with the Connection Broker.




Figure 10: Clicking on the Users link

4. When Figure 6 appears, click on **Create** to create a new user.




Figure 11: Clicking on the Create button

5. In the **Create a user** page that then appears (see Figure 7), enter the **Name** of the user.

Create User

Name
Limited Administrator

Role
Administrator ▾

.....

Login information

Login name
Limited

Password
.....

Re-type password
.....

.....

Other

Email address
.....

Notes
.....

Active user

Save

Figure 12: Creating a new Administrator user

6. Select the appropriate **Role** for the user from the drop-down menu. To enable the eG agent to execute tests on the Connection Broker, you need a user with **Administrator** privileges. So, select **Administrator** from the **Role** list (see Figure 7).

Monitoring Leostream Connection Brokers

7. Enter a **Login name** for the user, using the same format as used for logging into Microsoft Windows® operating systems. Login names are not case sensitive. While configuring a test for the Connection Broker, the **USER** and **PASSWORD** parameters should be configured with the **Login name** and **Password** specifications in Figure 7.
8. Enter an initial Password for the user. Users can subsequently change own password. Passwords are not case sensitive.
9. Enter an optional **Email address** for the user if you want them to receive messages from the Connection Broker. Users can subsequently change their email address settings.
10. Enter any **Notes** to save with the user definition.
11. Click **Save**.

Conclusion

This document has described in detail the monitoring paradigm used and the measurement capabilities of the eG Enterprise suite of products with respect to the **Leostream Connection Broker**. For details of how to administer and use the eG Enterprise suite of products, refer to the user manuals.

We will be adding new measurement capabilities into the future versions of the eG Enterprise suite. If you can identify new capabilities that you would like us to incorporate in the eG Enterprise suite of products, please contact support@eginnovations.com. We look forward to your support and cooperation. Any feedback regarding this manual or any other aspects of the eG Enterprise suite can be forwarded to feedback@eginnovations.com.